


A NOTE ON YIELDING



← Generic point P
 ← Cutting plane with normal $\vec{n}^{\text{oct}} = (\pm 1/\sqrt{3}, \pm 1/\sqrt{3}, \pm 1/\sqrt{3})$ with respect to $\underbrace{x_1^P - x_2^P - x_3^P}_{\text{principal stress axes}}$

- In principal coordinate system at P, state of stress is:

$$[\sigma] = \begin{bmatrix} \lambda_1 & 0 & 0 \\ 0 & \lambda_2 & 0 \\ 0 & 0 & \lambda_3 \end{bmatrix}$$

- On the cutting plane with normal \vec{n}^{oct} , we have

$$t_n = \vec{t} \cdot \vec{n}^{\text{oct}} = t_1 n_1 + t_2 n_2 + t_3 n_3$$

$$t_i = \sigma_{ji} n_j \Rightarrow t_i = \lambda_j \delta_{ij} n_i \Rightarrow t_1 = \lambda_1 n_1; t_2 = \lambda_2 n_2$$

$$t_3 = \lambda_3 n_3$$

$$\Rightarrow t_n = \lambda_1 n_1^2 + \lambda_2 n_2^2 + \lambda_3 n_3^2 = \frac{\lambda_1 + \lambda_2 + \lambda_3}{3} = \bar{\sigma}_H$$

$\bar{\sigma}_H \rightarrow$ hydrostatic stress ~ does not cause failure for the crystalline materials (actually failure is at HIGH value of $\bar{\sigma}_H$).

$\therefore t_s^{\text{oct}} =$ shear component of \vec{t} , such that

$$(t_s^{\text{oct}})^2 = |\vec{t}|^2 - t_n^2 = (\lambda_1^2 n_1^2 + \lambda_2^2 n_2^2 + \lambda_3^2 n_3^2) - t_n^2$$


$$= \frac{(\lambda_1^2 + \lambda_2^2 + \lambda_3^2)}{3} - \left(\frac{\lambda_1 + \lambda_2 + \lambda_3}{3}\right)^2$$

$$= \frac{1}{9} [(\lambda_1 - \lambda_2)^2 + (\lambda_2 - \lambda_3)^2 + (\lambda_3 - \lambda_1)^2]$$

* This plane is the OCTAHEDRAL plane, on which, "failure" happens due to ONLY t_s , as $t_n = \bar{\sigma}_H$ does not cause failure

* $t_s^{oct} \leq t_s^c$ can thus be a yield criterion which will work for the 3D - state of stress - its now about comparing two numbers!

- If this is true for $[\sigma]$ due to any loading, then it is true for a 1D - experiment also!




- Apply P, measure ΔL in gage region (at centre).

- Here we get recorded using a LOAD CELL

$\sigma_{11} = P/A$; $\sigma_{ij} = 0$ for all other stress components
 $\epsilon_{11} = \frac{\Delta L}{L}$ ($\Delta L/L$ obtained by strain gage or extensometer)

- Plot:



* σ_y obtained from graph by taking line // to loading line and cutting ϵ_{11} axis at $\epsilon_{11} = 0.002$.

σ_y - experimental; material dependent

$$\therefore (t_s^{oct})^2 = \frac{1}{9} [(\sigma_y - 0)^2 + 0 + (0 - \sigma_y)^2] = \frac{2}{9} \sigma_y^2$$

$$\Rightarrow \frac{1}{9} [(\lambda_1 - \lambda_2)^2 + (\lambda_2 - \lambda_3)^2 + (\lambda_3 - \lambda_1)^2] = \frac{2}{9} \sigma_y^2$$

$$\Rightarrow \frac{1}{2} [(\lambda_1 - \lambda_2)^2 + (\lambda_2 - \lambda_3)^2 + (\lambda_3 - \lambda_1)^2] = \sigma_y^2$$

σ_{RMS}^2 or $\sigma_{von-Mises}^2$

